Getting Started with StP/UML

Click on any Table of Contents entry to jump to the corresponding page.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Preface

This manual presents an introduction to Software through Pictures/Unified Modeling Language (StP/UML) for the first-time user. After completing this manual, you should:

- Be comfortable using the StP/UML user interface
- Be acquainted with many important features of StP/UML
- Understand basic Unified Modeling Language concepts and terminology
- Have created a basic object model
- Know where to find more information about StP/UML

This manual is part of a complete StP documentation set that also includes "Core" manuals: *Fundamentals of StP*, *Customizing StP*, *Query and Reporting System*, *Object Management System* and *StP Administration*. Basic information about the StP user interface is documented in *Fundamentals of StP*.

Intended Audience

The audience for this manual includes analysts and developers who use StP/UML to create object, dynamic, functional, and use case model diagrams.

The information in this manual assumes that you are familiar with:

- Fundamentals of Software through Pictures, including using diagram editors, the Object Annotation Editor, and annotation templates
- Object-oriented modeling, as documented in *Unified Modeling Language User Guide* (Booch et al 1998) and *Unified Modeling Language Reference Manual* (Rumbaugh et al 1998)
- Your operating system directory and file structures
- Conventions of your UNIX window manager or Windows NT

Refer to the appropriate documentation if you have any questions on these topics.

Typographical Conventions

This manual uses the following typographical conventions:

Table 1: Typographical Conventions

Convention	Meaning
Palatino bold	Identifies commands, buttons, and menu items.
`Courier`	Indicates system output and programming code.
`Courier bold`	Indicates information that must be typed exactly as shown, such as command syntax.
italics	Indicates pathnames, filenames, and ToolInfo variable names.
<angle brackets>	Surround variable information whose exact value you must supply.
[square brackets]	Surround optional information.

UNIX and Windows NT Conventions

StP is supported on UNIX and Windows NT operating systems. The following conditions apply:

- The terms “directory” and “folder” are synonymous.
- The terms “Enter” key and “Return” key are synonymous.
- This manual uses screenshots from StP for UNIX. If the equivalent Windows NT dialog box or window is substantially different, it is shown as well.
- This manual shows pathnames in UNIX format. Full Windows NT pathnames would include a drive letter at the beginning of each pathname.

Reader Comments

Aonix welcomes your comments about our documentation. If you have any suggestions for improving *Getting Started with StP/UML*, please complete the Reader Comments form included with your StP product documentation and send it to us.

Related Reading

Getting Started with StP/UML is part of a set of Software through Pictures documentation. For more information about StP/UML and related subjects, refer to the sources listed in Table 2.

Table 2: Further Reading

For Information About	Refer To
Using the StP Desktop	*Fundamentals of StP*, *Creating UML Models*
Using StP editors	*Fundamentals of StP*
Task-oriented approach to creating UML models with StP/UML	*Creating UML Models*
Generating C++ code from StP/UML models	*Generating and Reengineering Code*
Printing diagrams, tables, and reports	*Fundamentals of StP*, *Query and Reporting System*
Internal components of StP and how to customize an StP installation	*Customizing StP*
Using the Script Manager, writing Query and Reporting Language (QRL) scripts	*Query and Reporting System*
StP Object Management System (OMS)	*Object Management System*
Installing StP	*StP Installation Guide*
Interacting directly with the StP storage manager, Sybase SQL Server	*StP Guide to Sybase SQL Server*
Managing an StP installation	*StP Administration*
Annotation items	Object Annotation Editor Help menu

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

1 Creating an StP/UML Model

This tutorial guides you through the creation of an StP/UML model for an electronic mail system. It introduces you to basic tasks involving:

- StP/UML diagram and table editors
- The StP repository
- Diagram checking facilities
- Code generation

The tutorial also introduces basic concepts of the Unified Modeling Language. For a comprehensive introduction to UML modeling and semantics, refer to *Unified Modeling Language User Guide* (Booch et al 1998) and *Unified Modeling Language Reference Manual* (Rumbaugh et al 1998).

A complete version of the Email sample system is included on your StP/UML installation media. You may find it useful to review the system after completing this tutorial.

About StP/UML Models

UML models represent real-world objects and their interrelationships. There are five major, overlapping components of UML models:

- A requirements model—A behavioral view of system requirements interacting with external agents
- A logical model—A conceptual view of the entire domain of activity that is not concerned with physical implementation

- A physical model—A material view of the details of implementation, such as the hardware and software components of a system
- A static model—A descriptive view of the characteristics of parts of the domain of activity
- A dynamic model—A behavioral view of the parts of the domain of activity

StP/UML Diagrams

Each of the five components of a UML model represents a view of the entire model. In StP/UML, each view is represented by one or more of the following types of diagrams:

- Use Case diagram
- Class diagram
- Interaction diagrams (collaboration and sequence)
- State diagram
- Activity diagram
- Implementation diagrams (component and deployment)

Use Case Diagrams

Use case diagrams model the interactions between the system and external agents. They provide an overview of user requirements and system behavior that is helpful in the early phases of the system development life cycle.

Class Diagrams

A class diagram is a graphical representation of the classes in the real-world domain and the relationships between these classes. Class diagrams can have associated class tables, which allow you to capture the full definitions of a class's attributes and operations. Class diagrams and class tables are key components in the logical-static view of a system.

Interaction Diagrams

Interaction diagrams show groups of objects interacting through message passing. The two types of interaction diagrams—sequence and collaboration—show different views of object interaction. Sequence diagrams show a dynamic view; collaboration diagrams show a static view.

Sequence Diagrams

A sequence diagram shows the order of messages sent between objects. It emphasizes control flow and control information such as conditions and iterations. Sequence diagrams complement state diagrams in presenting a logical-dynamic view of a system.

Collaboration Diagrams

A collaboration diagram is a graphical representation of the objects in an interaction and the message pathways between them. It emphasizes message types, concurrency, visibility, and return values. Collaboration diagrams complement class diagrams in the logical-static view of a system.

State Diagrams

A state diagram represents the potential states of an object and the events that transform the object from one state to another. State diagrams can have associated tables, which provide detailed information about individual states. State diagrams and state tables present a logical-dynamic view of the system.

Activity Diagrams

An activity diagram is a variation of a state diagram used to model the procedural flow of a task. Using activity diagrams, you can model the steps required to perform an operation, a use case, or a behavior spanning several use cases. Activity diagrams present a logical-dynamic view of the system.

Contents	Index	Go Back	Previous Page	Next Page	Using StP Help	List of Manuals	Quit Window

Implementation Diagrams

Implementation diagrams show the physical design of the system. There are two types of implementation diagram: component diagrams, which show software structure, and deployment diagrams, which show hardware configuration. Component and deployment diagrams present a physical-static view of the system.

Component Diagrams

A component diagram shows the binary, executable, and source code components of the system and the dependencies between these software components.

Deployment Diagrams

A deployment diagram shows the allocation of software to hardware and the interconnections between the hardware components.

Summary of UML Diagrams

Table 1 provides a summary of UML diagram types.

Table 1: StP/UML Diagram Types

Diagram	Purpose	Logical/Physical/ Requirements	Dynamic/ Static
Use Case	Shows interactions between the system and its users	Requirements	Static
Class	Shows classes and their relationships	Logical	Static
Sequence	Shows the order of message passing among interacting objects	Logical	Dynamic
Collaboration	Shows the objects in an interaction and their message pathways	Logical	Dynamic and Static

Table 1: StP/UML Diagram Types (Continued)

Diagram	Purpose	Logical/Physical/ Requirements	Dynamic/ Static
State	Shows the potential states of an object, the events that cause a transition from one state to another, and the actions that result from the transition	Logical	Dynamic
Activity	Traces the execution of a task or method; can show parallel processing	Logical	Dynamic
Component	Shows software structure and dependencies	Physical	Static
Deployment	Shows hardware configuration and dependencies	Physical	Dynamic and Static

Extending UML Models

The Unified Modeling Language includes a standard set of modeling elements such as packages, classes, components, and dependencies. You can extend the semantics of these elements using constraints, tagged values, and stereotypes.

Constraints allow you to restrict the properties of elements in your model; tagged values allow you to add properties. Stereotypes allow you to define new modeling elements based on the existing set.

StP/UML supports all of the Unified Modeling Language's predefined constraints, tagged values, and stereotypes. In addition, StP/UML supports user-defined extensions. You use the Stereotype Editor to define stereotypes and stereotype hierarchies. You use property sheets to define tagged values and constraints.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Generating Code for a UML Model

Using a valid UML class diagram and class table, you can generate C++ code. In this tutorial, you generate C++ code for a class in the Email application.

For detailed information about generating code for UML models, see the *Generating and Reengineering Code* manual.

Continuing the Tutorial

In this chapter, you received an overview of StP/UML. You learned about:

- The components of a UML model: requirements, logical, physical, static, and dynamic
- The types of StP/UML diagrams and tables
- The mechanisms for extending UML modeling elements: constraints, tagged values, and stereotypes
- Generating code from UML models

In Chapter 2, you begin modeling the Email application.

2 Beginning the Email Model

In this chapter, you examine the problem statement provided for the Email application, set up your system directory, and begin your Email model by creating a use case diagram. The use case diagram provides an overview of user requirements and system behavior.

Requirements for the Email Application

This section contains a list of the requirements for the Email application. Review these requirements now. Later, as you create your Email model, you refer to these requirements to determine its classes and relationships.

The requirements for the Email application include:

- The Email system must provide an electronic means of sending textual messages to users.
- Each user must have a name and a mailbox that can contain any number of messages.
- When logged in, a user must be able to ask to see the contents of his or her mailbox and, in response, the system should present a list of message subject lines.
- The user must be able to send a message to another user. The Email system must prompt the user for the name of the recipient, a subject line, and the body of the message.
- The Email system must check the address of the recipient. If the address is not valid, the system must display an error message.
- The user must be able to forward a message to another user.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

- The Email application must support "conferences," which allow users to post messages to electronic bulletin boards.
- Conferences must have subject names.
- When logged in, a user must be able to join any conference.
- The logged-in user must be able to ask for a list of users and conferences.

Using the StP Desktop

The Software through Pictures (StP) Desktop, shown in Figure 1, provides access to StP/UML editors and commands, StP Core commands, and StP utilities.

Figure 1: The StP Desktop



In this tutorial, you use the StP Desktop to:

- Start the StP/UML editors
- Generate C++ code for the Email system

For a complete description of the StP Desktop, refer to *Creating UML Models*.

Starting the StP Desktop from Windows NT

To start the StP Desktop from Windows NT:

1. Click on the Start menu.
2. Choose the Programs menu.
3. Choose **StP UML** from the Aonix Software through Pictures menu.

Starting the StP Desktop from UNIX

To start the StP Desktop from UNIX, type the following command on the command line:

```
stp [&]
```

Creating a System for Your Model

Before beginning the exercises in this tutorial, you must create and set a system in which to work. A system contains the database and files associated with your model.

If you do not have the privileges needed to create a system, ask your system administrator to create a system for use with this tutorial and to add you as a repository user.

For more information about systems, see *StP Administration*.

Creating a System

To create a system:

1. Select the Administer category on the StP Desktop.
   A list of tools appears.

Figure 2: Administer Category



2. Select the Administer System tool.
3. Choose **Create System** from the Commands menu.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Figure 3: Create System Command



The Create System dialog appears.

4. Type **`Tutorial`** in the System input box, as shown in Figure 4.

Figure 4: Create System Dialog



5. Click **OK**.
   A new system called *Tutorial* is created.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Setting the System

To set the current system to the *Tutorial* system:

1. Choose **Set Project/System** from the File menu on the StP Desktop.
   The Set Project/System dialog appears.

Figure 5: The Set Project/System Dialog



2. Select *Tutorial* from the Directories and Systems scrolling list.
3. Click **OK**.
   The current system is set to *Tutorial* and the dialog is dismissed.

   You are now ready to begin creating your model.

About the Use Case Editor

You begin your model by creating a use case diagram for the Email system. Use case diagrams model the interactions between the system and external agents. By beginning your model with a use case diagram, you gain an understanding of how the system will be used.

You use the Use Case Editor to create the diagram. For a complete description of the Use Case Editor, see *Creating UML Models*.

Starting the Use Case Editor

You can start the StP/UML editors from the StP Desktop or, if you are a UNIX user, from the command line. In this tutorial, you start all the editors from the StP Desktop. For instructions on starting an StP/UML editor from the UNIX command line, refer to the chapter that describes the editor in *Creating UML Models*.

To start the Use Case Editor:

1. Select the Model category on the StP Desktop.
   A list of tools appears.
2. Select Use Case Diagrams, as shown in Figure 6.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Figure 6: Starting the Use Case Editor



3. Choose **Start New Editor** from the Commands menu.

Figure 7: Start New Editor Command



The Use Case Editor window appears, as shown in Figure 8.

Figure 8: StP Use Case Editor Window



The name of the system and the diagram appear in the title bar in the format *system name: diagram name*. Since you have not yet named the diagram, the term *Noname* appears instead of the diagram name.

Naming the Diagram

You use the Save Diagram dialog to name and save the diagram.

To name the diagram:

1. Choose **Save As** from the File menu.
   The Save Diagram dialog appears.
2. Type **`EmailSystem`** in the Selection box, as shown in Figure 9.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Figure 9: Naming the Diagram



3. Click **OK**.
   The name of the diagram, *EmailSystem*, appears in the Use Case Editor title bar, as shown in Figure 10.

Figure 10: Use Case Editor with Diagram Name



Creating a Use Case Diagram

A use case diagram describes interactions between actors and the system. An actor is an entity outside the system that uses the system to perform various tasks. Each task is represented by a use case. For example, a user (the actor) might use the Email application to send a message (the use case).

By beginning your model with a use case diagram, you gain an understanding of how the Email system will be used. Use case diagrams help you ensure that your model captures the requirements of the application's users.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

For this tutorial, you model two use cases:

- Sending a message
- Forwarding a message

In a complete UML model, you would try to identify all possible actors and use cases for the system. Additional use cases in an Email system might include:

- Saving a message
- Deleting a message
- Joining a conference

Inserting Actors

In this example, the actor is the user who is sending or forwarding the message. Begin your use case diagram by inserting the actor *User*.

To insert and label an actor:

1. Drag an actor symbol into the drawing area.
   An actor symbol appears in the drawing area, surrounded by selection handles, as shown in Figure 11.

   Figure 11: An Actor Symbol

   

2. Type the label `User` on the selected actor symbol.
3. Click the left mouse button to terminate the label editing mode.
   For the remainder of the tutorial, whenever you label a symbol, use the left mouse button to terminate editing.

   Your diagram should resemble Figure 12.

Figure 12: Labeled Actor



Modeling Use Cases

A use case symbol represents one or more ways that an actor can use a system. In this tutorial, you model use cases called *Send_Message* and *Forward_Message*.

To model a use case:

1. Drag a use case symbol from the symbol list into the drawing area, placing it to the right of *User*.
2. Label the use case **`Send_Message`**.
3. Place a second use case symbol above *Send_Message* and label it **`Forward_Message`**.
   Your diagram should resemble Figure 13.

   Figure 13: Labeled Use Cases



Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Modeling the System

The *User* actor is external to the Email application, while the *Send_Message* and *Forward_Message* use cases are functions contained within the application. You can represent the boundaries of the Email system using the This System symbol.

Figure 14: This System Symbol



To represent the system:

1. Drag a This System symbol into the drawing area and place it to the left of *Forward_Message*.
2. Label the symbol *Email*.
   Your diagram should resemble Figure 15.

   Figure 15: Labeled System Symbol



Scaling Symbols

You need to scale the This System symbol so that it encloses the *Forward_Message* and *Send_Message* use cases.

To scale a symbol:

1. Select the This System symbol.
   Selection handles appear on the symbol.
2. Press the left mouse button on the lower right selection handle.
3. Drag the bounding box to the desired size.
4. Release the mouse button.
   Your diagram should resemble Figure 16.

Figure 16: Scaled System Symbol



Modeling Communication

To show that an actor interacts, or "communicates," with a use case, you draw an arc from the actor to the use case symbol.

To insert a communication link:

1. Using the left mouse button, drag an Arc symbol into the *User* actor symbol.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

2. Release the mouse button.
   This action attaches one end of the arc to the actor symbol.
3. Move the pointer into the *Send_Message* use case symbol.
4. Click to attach the opposite end of the arc to the use case symbol.
   Selection handles appear on the arc.
5. Click the left mouse button to dismiss the selection handles.
   Your diagram should resemble Figure 17.

Figure 17: Communication Link



Alternate Method for Inserting Arcs

You might find it useful to experiment with a shorter method for inserting arcs.

To insert an arc using the alternate method:

1. Move the pointer to the *User* actor symbol.
   When the pointer is over the symbol, it changes to a circle.
2. While pressing the Control key on your keyboard, click on the *User* actor symbol.

3. Release the Control key.
   This action attaches one end of the arc to the actor symbol.
4. Drag the arc into the *Forward_Message* use case symbol.
5. Click to attach the arc to the use case symbol.
   Your diagram should resemble Figure 18.

Figure 18: Alternate Method for Inserting Links



Modeling Relationships between Use Cases

Two kinds of relationships can exist between use cases:

- "Extends" relationships, in which one use case may, under special circumstances, include the behavior of another use case.
- "Uses" relationships, in which one use case always includes the behavior of another use case.

Setting the Default Arc Type

You can select the type of arc you want to draw (uses or extends) using the Default Arc Type dialog. Alternatively, you can change an arc that you have already drawn from one type to another using the **Replace** command. You use both methods in this tutorial.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

To set the default arc type:

1. Choose **Default Arc Type** from the Options menu.
   The Default Arc Type dialog appears.

Figure 19: Default Arc Type Dialog



2. Choose **Uses** from the Arc Types list.
   The arc type is highlighted.
3. Click **OK**.

Indicating a "Uses" Relationship

The requirements state that a user must be able to forward an email message to another user. For the system, forwarding a message involves copying an existing message into the body of a new message, highlighting the copied text, and sending the new message.

In sending the new message, *Forward_Message* uses the same behavior as the *Send_Message* use case. Rather than duplicating the specifications for sending an email message, you can indicate that *Forward_Message* "uses" the *Send_Message* behavior.

To model the uses relationship, draw an arc from *Forward_Message* (the client use case) to *Send_Message* (the use case that is used). StP automatically adds a pointer to the target use case and adds the label «uses» to the relationship arc.

Your diagram should resemble Figure 20.

Figure 20: Uses Relationship



The guillemets (« ») surrounding the label indicate that the uses relationship is a variant, or stereotype, of a standard UML modeling element (in this case, a dependency relationship). Stereotypes can be assigned to a number of UML modeling elements to indicate special semantics. You will learn more about stereotypes in a later chapter.

Indicating an "Extends" Relationship

In the Email system, if a user attempts to send a message to an invalid address, the system displays an error message. The error message does not occur in a typical *Send_Message* transaction; it is displayed only when an invalid address is used. You can model this behavior as a separate use case, *Invalid_Address*, that extends the behavior of the *Send_Message* use case in certain circumstances.

To model an extends relationship:

1. Place a use case symbol below *Send_Message* and label it **`Invalid_Address`**.
   You may have to scale the system symbol to make room for the new use case.

2. Draw an arc from the *Invalid_Address* use case to the *Send_Message* use case.
   An arc appears with the label «uses».
3. With the arc still selected, choose **Replace** from the Edit menu.
   The label on the arc changes to «extends».

   Your diagram should resemble Figure 21.

Figure 21: Extends Relationship



Saving the Diagram

When you save a diagram (or table, in subsequent chapters), it is committed to the repository, which is the central store of all the information associated with your diagram. By storing diagram and table information in the repository, you make it available to other diagrams and programs such as the StP Query and Reporting System (QRS). The repository also enables checking programs to make sure the elements defined in your model are used properly elsewhere in the system. For more information about the repository, see *Object Management System*.

To save your diagrams and tables, use one of the following methods:

- Choose **Save** from the editor File menu.
- Use the accelerator Ctrl+s.
- Display the File menu and type S, the mnemonic for the **Save** command.

Using one of these methods, save your use case diagram now. For the remainder of the tutorial, whenever you save a diagram, you can use any of these methods. (For a complete description of accelerators and mnemonics, see *Fundamentals of StP*.)

After saving a diagram or table, you can exit the editor and recall the diagram or table at a later time. If you exit an editor without saving your work, any changes made since the last **Save** are lost.

Exiting the Editor

Exit the Use Case Editor by choosing **Exit** from the File menu.

Continuing the Tutorial

In this chapter, you:

- Reviewed the requirements for the Email application
- Started the StP Desktop
- Created and set up your Tutorial system
- Created a use case diagram

In the next chapter, you create a class diagram for the Email system.

3 Creating a Class Diagram

In this chapter, you create a class diagram for the Email application.

About the StP/UML Class Editor

The StP/UML Class Editor enables you to draw classes and the relationships between them. In this chapter, you model the classes and relationships for the Email application.

For this tutorial, you identify and model all of the Email application's packages, classes, attributes, operations, and relationships at one time. Typically, this process is an iterative one; you would identify and model classes, attributes, and operations throughout the modeling process.

Starting the Class Editor

You start the Class Editor from the StP Desktop.

To start the Class Editor:

1. Select the Model category on the StP Desktop.
   A list of tools is displayed.
2. Select Class Diagrams.
3. Choose **Start New Editor** from the Commands menu.
   The Class Editor appears, as shown in Figure 1.

Figure 1: The Class Editor



Naming the Diagram

Use the Save Diagram dialog to name the diagram *Email*. If necessary, refer to "Naming the Diagram" on page 2-9.

Setting the Default Arc Type

Use the procedure described in "Setting the Default Arc Type" on page 2-17 to set the Class Editor's default arc type to **Association**.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Identifying Class Packages

The first step in creating a UML model is to identify the application's classes. There is more than one way to approach this task. You can identify the application's classes directly using the information available to you in the requirements and in use case diagrams. Another approach is to first determine categories of classes based on the application's architecture or services, and then identify the classes in each category. In a class diagram, you represent this kind of logical grouping as a "package" (the category) with contents (the classes).

A package is a general purpose symbol used in many different StP/UML diagrams to show containment. It is represented by a folder icon.

Figure 2: Package Symbol



In this tutorial, you begin by identifying the Email application's packages. Since this is a simple application, it has only two packages:

- *ReuseLibrary*—Contains classes that come from a reuse library
- *Application*—Contains the classes that are part of the Email application

Although you identify all of the Email application's classes and packages at the beginning of this tutorial, typically this process is iterative. You can identify and model classes and packages at any time during the development of your model.

Modeling Packages

To model packages:

1. Drag a package symbol into the drawing area.
2. Label the symbol **`Application`**.

3. Drag another package symbol into the drawing area, and place it to the right of the *Application* package symbol.
4. Label this symbol `ReuseLibrary`.
   Your diagram should resemble Figure 3.

Figure 3: Email Class Diagram with Packages

Modeling Dependencies Between Packages

The *Application* package relies on the *ReuseLibrary* package for services. You model this dependency by drawing an arc from the package requiring services (*Application*) to the package providing services (*ReuseLibrary*).

The relationship between packages is always a dependency relationship.

To model a dependency between packages:

1. Drag an Arc symbol into the *Application* package and release the mouse button.
   This action attaches one end of the arc to the *Application* package.
2. Move the pointer into the *ReuseLibrary* package and click the left mouse button.
   This action attaches the opposite end of the arc to the *ReuseLibrary* package. Selection handles appear on the arc.
3. Choose **Replace** from the Edit menu to change the arc from an association to a dependency.
   The arc changes to a dashed line with an arrow pointing to the *ReuseLibrary* package.

   Your diagram should resemble Figure 4.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Figure 4: Packages with Dependency Relationship



Adding Contents to Packages

In the following sections, you add contents to the packages. Package contents can be classes or other packages. The *Application* and *ReuseLibrary* packages contain classes only.

Adding Contents to the ReuseLibrary Package

The *ReuseLibrary* package contains two classes:

- *Collection*—This class holds a collection of objects. In the Email application, it holds a collection of messages in a user's mailbox.
- *CollIterator*—This class iterates through a collection of objects. In the Email application, it iterates through a collection of messages in a user's mailbox in order to print them.

To add contents to the *ReuseLibrary* package:

1. Scale the *ReuseLibrary* package so it can accommodate two classes.
2. Drag a class symbol into the package.
3. Label the class `Collection`.
4. Drag a second class symbol into the package.
5. Label the class `CollIterator`.
   Your diagram should resemble Figure 5.

Figure 5: ReuseLibrary package with Contents



6. Choose **Save** from the File menu to save your diagram.

Adding Contents to the Application Package

The *Application* package contains all of the classes that are part of the Email application. To avoid crowding the *Email* diagram, you draw the contents of the *Application* package on a separate class diagram.

Creating a New Diagram

To create a new diagram from within the Class Editor:

1. Choose **Open** from the File menu.
   The Open Diagram dialog box appears.
2. Type **`Application_1`** in the Selection text field, as shown in Figure 6.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Figure 6: Open Diagram Dialog



3. Click **OK**.
   The dialog is dismissed and a new class diagram named *Application_1* appears in the editor window.
4. Choose **Save** from the File menu.
   You are now ready to begin creating your class diagram.

Modeling Classes

The *Application* package contains all of the classes that are part of the Email application. Try to identify the classes in this package by reviewing the requirements in Chapter 2. If you need help, refer to the following list:

- Conference
- Mailbox

- MailSystem
- Message
- Receiver
- User

Inserting Class Symbols

Begin the class diagram by inserting a symbol for each class in the *Application* package.

To model classes:

1. Select the Class symbol in the Symbol List.
   The Class symbol is highlighted.
2. Move the pointer into the drawing area.
3. While pressing Alt+Ctrl, click the left mouse button.
   This accelerator enables you to insert the currently selected symbol (in this case, a class symbol) in your diagram.
4. Insert five additional class symbols, placing them so that your diagram resembles Figure 7.
   A total of six class symbols should appear in the drawing area. You may need to enlarge your drawing area to fit all the symbols. For instructions, refer to the following section, "Using Zoom."

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Figure 7: Inserting Classes



Using Zoom

Use the Zoom features to enlarge your view of the drawing area and provide more space for inserting objects. The Zoom features allow you to enlarge the drawing area by a specific percentage or to zoom up or down by set increments.

To use Zoom:

1. Display the View menu.
2. Drag the pointer to **Zoom** and across to the arrow to display its cascade menu.
3. Choose a selection from the Zoom cascade menu to enlarge the view of the drawing area.

Labeling Classes

To label class symbols:

1. Select the topmost class symbol on your diagram and type `MailSystem`.
2. Label the remaining class symbols so that your diagram resembles Figure 8.

Figure 8: Labeled Class Symbols



Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Modeling Attributes of Classes

Attributes represent the data held by objects in a class.

For example, each message must have a subject line and a body. Therefore, *subject* and *body* are modeled as attributes of the *Message* class.

Try to determine the attributes of the Email application's classes from the requirements. If you need help, refer to Table 1.

Table 1: Email Model Class Attributes

Class	Attributes
MailSystem	conferences users
Receiver	name mail_system mailbox current_sender
Mailbox	name messages
User	name mail_system mailbox current_receiver
Conference	subject
Message	body subject from to

Inserting Class Attributes

There are three methods for inserting class attributes:

- Inserting attribute symbols using the Symbol List
- Using the Alt+Ctrl+a keyboard accelerator
- Using the Class Table Editor (CTE)

The instructions in this chapter tell you how to insert attributes using the Symbol List. If you prefer, you can use the keyboard accelerator. For more information about using keyboard accelerators, see *Fundamentals of StP*.

In Chapter 5, you use the CTE to add additional details about the Email application's attributes.

Inserting Attributes Using the Symbol List

To insert attributes on your diagram using the Symbol List:

1. Drag an attribute symbol from the symbol list into the *MailSystem* class.
   The class symbol resizes to fit the attribute. Selection handles appear on the attribute symbol.

Figure 9: Attribute Symbol with Selection Handles



2. Label the attribute symbol `conferences`.
   The MailSystem class should resemble Figure 10.

Figure 10: Labeled Attribute



3. Drag another attribute symbol into the MailSystem class.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

The attribute symbol automatically positions itself under the attribute you inserted in step 1.

4. Label the attribute `users`.
5. Using Table 1 as a guide, specify the attributes of the remaining classes.
   Be sure to insert a new attribute symbol for each attribute in the class (rather than entering multiple lines on one attribute symbol).

   Your diagram should resemble Figure 11.

Figure 11: Completed Attributes for the Email Model



Moving Symbols

As your class symbols grow, you may find it necessary to reposition them. Use the procedures in this section to move symbols individually or in groups.

Moving a Symbol

To move a symbol:

1. Click on the symbol.
   Selection handles appear.
2. Press the left mouse button and drag the symbol to the desired position.

Selecting a Group of Symbols

You can add to a selection by pressing the Shift key and selecting other symbols, or you can use a bounding box to select all of the symbols in an area of the diagram at one time.

To use a bounding box:

1. Move the pointer to a corner of the area you want to select.
2. Press the left mouse button.
3. Drag the pointer diagonally across the area to be selected.
   A bounding box appears around the perimeter of the selected area.
4. Release the left mouse button.
   All the symbols and arcs within the area display handles.

Moving a Group of Symbols

To move a group of selected symbols:

1. Move the pointer over one of the selected symbols.
   The pointer changes to a circle.
2. Press the left mouse button and drag the symbol.
   As you drag the symbol, all of the selected symbols move in tandem.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Modeling Operations

An operation is an action performed by objects in a class. For example, a user can send messages and join conferences. Therefore, *send_msg* and *join_conf* are modeled as operations of the *User* class.

Try to determine the operations of the Email application's classes from the requirements. When you are finished, compare your list against the one in Table 2.

Table 2: Email Model Class Operations

Class	Operations
MailSystem	find_user find_conf login_user delete_user_or_conf create_user_or_conf start
Receiver	read_msg print_mbx receive_msg
Mailbox	add_msg print_mbx print_msg empty
User	string start send_msg join_conf
Conference	string
Message	send_to_rec print

Inserting Class Operations

There are three methods for inserting class operations:

- Inserting operation symbols using the Symbol List
- Using the Alt+Ctrl+a keyboard accelerator
- Using the Class Table Editor (CTE)

The instructions in this chapter tell you how to insert operations using the Symbol List. If you prefer, you can use the keyboard accelerator.

In Chapter 5, you use the Class Table Editor to add details about the Email application's operations.

Inserting Operations Using the Symbol List

To insert operations on your diagram using the Symbol List:

1. Drag an operation symbol from the symbol list into the *MailSystem* class.

   The class symbol resizes to fit the operation. Selection handles appear on the operation symbol.

2. Label the operation **`find_user`**.

   StP automatically appends parentheses to the label to represent the operation's arguments. Later in this tutorial, you define operation arguments using the Class Table Editor.

   Figure 12: Labeled Operation

   

3. Using Table 2 as a guide, insert the remaining operations for the *MailSystem* class.

   Be sure to insert a new operation symbol for each operation in the class.

   The *MailSystem* class symbol should resemble Figure 13.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Figure 13: MailSystem Operations



4. Using Table 2 as a guide, specify the operations for the remaining classes.

   As your diagram grows, you may find it necessary to zoom to a lower percentage or to use the **Fit Diagram in Window** command. These options are available from the View menu.

   Your diagram should resemble Figure 14.

Figure 14: Completed Operations for the Email Model



Modeling Associations

In addition to classes, you must also identify and understand the associations, or relationships, between classes. For example, users of the Email application can send messages. Therefore, an association exists

between the *User* class and the *Message* class. Associations are represented by connection arcs on your diagram.

Refer to the requirements to determine the associations between the classes in your diagram. If you need help, refer to Table 3.

Table 3: Email Model Associations

Class	Is Associated With	Arc Label
MailSystem	User	*Is_Logged_Onto_By*
User	Conference	*Joins*
	Message	*Sends*
Receiver	Mailbox	*Owns*
Mailbox	Message	*Holds*

Inserting An Association Arc

To insert an association arc:

1. Drag an Arc symbol into the *User* class and release the mouse button.
   This action attaches one end of the association arc to the *User* class.
2. Move the pointer into the *Message* class and click the left mouse button.
   This action attaches the opposite end of the association arc to the *Message* class. Selection handles appear on the arc.

Figure 15: Association Arc

Inserting Orthogonal Arcs

Orthogonal arcs consist of horizontal and vertical line segments. An orthogonal arc makes it possible for you to draw arcs without intersecting other symbols in the diagram.

To set orthogonal arcs:

1. Choose **Drawing Area** from the Options menu.
   The Drawing Area Options dialog appears.

Figure 16: Drawing Area Options Dialog



2. Select **Orthogonal Arcs**.
3. Click **OK** to apply the change and dismiss the dialog box.

To insert an orthogonal arc:

1. Drag an Arc symbol into the *User* class and release the mouse button.
2. Drag the arc up and to the right into the *MailSystem* class and click the left mouse button.
   This action creates an orthogonal arc between the *User* and *MailSystem* classes, as shown in Figure 17.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Figure 17: Orthogonal Arc



You do not need to insert another orthogonal arc in your diagram. To deselect orthogonal arcs:

1. Redisplay the Drawing Area Options dialog.
2. Deselect the **Orthogonal Arcs** option.
3. Click **OK**.

Inserting the Remaining Associations

Using Table 3 as a guide, insert the remaining associations into your diagram. If you wish, you may draw the associations using the accelerated method of inserting arcs, as described on page 2-16.

Aligning the Links on Your Diagram

The **Align Links** command provides a quick method for straightening the arcs on your diagram.

To use this command:

1. Display the Drawing Area menu by clicking the right mouse button anywhere in the drawing area.
   The Drawing Area menu appears, as shown in Figure 18.

   Figure 18: Drawing Area Menu

   

   For additional information about the Drawing Area menu, see *Fundamentals of StP*.

2. Choose **Align Links**.
   The links on the diagram are aligned.

   Your diagram should resemble Figure 19.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Figure 19: Inserting Association Arcs



Labeling Associations

Associations are bidirectional. The label of an association can imply a direction, but it can also be read to show the other direction. For example, a user *sends* a message, and conversely, a message *is sent by* a user. Either direction is acceptable, but to improve readability, try to use active verbs when labeling associations.

Draw your diagram so that association labels read from left to right or top to bottom. To have all the labels for this diagram read from left to right or top to bottom, you need to use one label, *Is_Logged_Onto_By*, that is not an active verb.

To label the association arc between the *MailSystem* and *User* classes:

1. Select the vertical portion of the association arc between *MailSystem* and *User*.
2. Type **`Is_Logged_Onto_By`**.
   The label appears on the arc.
3. Click the left mouse button to terminate the label-editing mode.
4. Label the remaining association arcs on your diagram, using Table 3 as a guide.
   Your diagram should resemble Figure 20.

Figure 20: Labeling Associations



Setting Display Mark Options

Display marks are used to indicate a variety of information. In the remainder of this chapter, you add information to your object model that has associated display marks.

You can set options for display marks to decide which marks are:

- Updated automatically
- Updated on demand (by choosing **Update Display Marks** from the Edit menu)
- Not displayed

You set display mark options using the Display Mark Options dialog box. For this tutorial, you set the display marks to be updated automatically.

To set display mark options:

1. Choose **Display Marks** from the Options menu.
   The Display Mark Options dialog appears.
2. Move all of the display marks into the Continuous Update window by using the appropriate arrows.
   The Display Mark Options dialog should resemble the one shown in Figure 21.

Figure 21: The Display Mark Options Dialog



3. Click **OK** to apply the change and dismiss the dialog.

For more information about the Display Mark Options dialog, refer to *Fundamentals of StP.*

Defining Association Properties

An association can have various properties, including:

- Role Names
- Multiplicity
- Qualifiers
- Navigability
- Constraints

In the following sections, you add these properties to associations in your diagram using UML menu commands and the Properties dialog box. The Properties dialog box enables you to change the characteristics of a selected relationship and apply all the changes at once.

For a complete description of the association properties that can be defined using the Properties dialog, see Creating UML Models.

Naming Association Roles

Each end of an association relationship is a role. A role is the function that one end of a relationship assumes with respect to the other end of the relationship. Role names are optional; you can provide each role with a role name, but you are not required to do so. The advantage of providing role names is that they clarify the meaning of the relationship.

In the *Email* application, you give role names to the relationship between the *User* and *Message* classes. In this relationship, *User* assumes the role of sender and *Message* assumes the role of mail message.

Specifying Role Names

To specify association role names:

1. Select the arc between the *User* and *Message* classes.
   Selection handles appear on the arc.
2. Choose **Create Association Roles** from the UML menu.

Figure 22: The Create Association Roles Command



Text frames with selection handles appear on each side of the arc.

Figure 23: Text Frames



3. Select the text frame next to the *User* class.
4. Type the role name **`Sender`**.
5. Click the left mouse button to terminate the label editing mode.
6. Select the text frame next to the *Message* class.
7. Type the role name **`Mail Message`**.
   Your diagram should resemble Figure 24.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Figure 24: Role Names on the Diagram



Indicating Multiplicity on Roles

In an association, a single instance of one class can relate to instances of the other class one or more times. The number of instances that can relate at one time is called the “multiplicity” of the association.

Table 4 lists the conventional notation for different types of multiplicity.

Table 4: Multiplicity Types

Type	Description	Notation
Unspecified	Default	None
Exactly One	A single instance of a class participates in the association	1
Many	More than one instance of a class participates in the association	*
Optional	A single instance of a class may or may not participate in the association	0..1
One or More	One or more instances of a class may participate in the association	1..*
Explicit Multiplicity (single value)	A specific number of instances of a class may participate in the association	N (where N is an integer)

Table 4: Multiplicity Types (Continued)

Type	Description	Notation
Explicit Multiplicity (range)	The number of participating instances of a class falls within a specified range	N..N (where N is an integer)

Assigning Multiplicity to Roles

In this example, you assign a multiplicity value of one to the *Sender* role and a multiplicity value of many to the *Mail Message* role, because a *Sender* can send many *Mail Messages*, but a *Mail Message* can be sent by only one *Sender*.

You use the Properties dialog box to specify multiplicity.

To assign multiplicity to an association:

1. Select the arc between the *User* and *Message* classes.
   Selection handles appear on the arc.
2. Use one of the following methods to open the Properties dialog box:
   - Choose **Edit Properties** from the UML menu
   - Double-click on the selected relationship
   - Use the accelerator Alt+Ctrl+P

   The Properties dialog box appears. The name of the association appears in at the top of the dialog box. The names of the classes joined by the association as well as the association role names appear in read-only fields beneath the association name.

Figure 25: The Properties Dialog for Associations



3. Click on the Multiplicity text field for *Message*.
4. Type `*`.
   This establishes a multiplicity of many for the *Mail Message* role.
5. Click on the Multiplicity text field for *User*.
6. Type `1`.
   This establishes a multiplicity of exactly one for the *Sender* role.

   The Properties dialog should resemble the one shown in Figure 26.

Figure 26: Specifying Multiplicity



7. Click **OK**.
   The dialog is dismissed and the properties are applied. The multiplicity display marks appear on the diagram, as shown in Figure 27.

Figure 27: Multiplicity Display Marks



Specifying Additional Multiplicity

Add additional multiplicity to the Email diagram to indicate:

- A user can have only one mail system, but a mail system can have one or more users (multiplicity of exactly one to one or more).
- A user can join many conferences, and a conference can have many users (multiplicity of many to many).
- A message can have only one mailbox; a mailbox can contain up to a hundred messages, or it may be empty (multiplicity of one to a specified range).

When you are finished, your diagram should resemble Figure 28.

Figure 28: Assigning Multiplicity to Associations



Qualifying an Association

A qualifier is an attribute whose unique value identifies a single object instance. For example, in the relationship between *MailSystem* and *User*, the attribute that uniquely identifies a user of the mail system is *name*.

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

A qualifier appears as a display mark on a diagram. It is a labeled box on the end of the association arc opposite the class it qualifies.

Inserting a Qualifier

To insert a qualifier:

1. Select the arc between the *MailSystem* and *User* classes.
   Selection handles appear on the arc.
2. Choose **Edit Properties** from the UML menu.
   The Properties dialog box appears.
3. Click on the Qualifier text field for the *MailSystem* class.
4. Type **`Name`**.
   The Properties dialog should look like the one in Figure 29.

Figure 29: Designating Qualifiers



5. Click **OK**.

The dialog is dismissed and the property is applied. The qualifier appears in the diagram next to the *MailSystem* class, as shown in Figure 30.

Figure 30: Inserting a Qualifier



Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

Indicating Navigability

An association can be bidirectional (used in both directions) or unidirectional (used in only one direction). You indicate the direction of an association by specifying the “navigability” of each of its roles. In bidirectional associations, both association roles are navigable. In unidirectional associations, only one association role is navigable.

For example, in the Email system, the *User* class requests services from the *Conference* class, but the *Conference* class does not request services from the *User* class. In this unidirectional association, only the role representing *Conference* (the class that receives service requests) is navigable.

Bidirectional and unidirectional associations are implemented differently, so it is important to specify role navigability if you plan to generate code from your StP/UML model. For complete information about annotating your model for code generation, see *Generating and Reengineering Code*.

To indicate navigability on an association:

1. Select the arc between the *User* and *Conference* classes.
   Selection handles appear on the arc.
2. Choose **Edit Properties** from the UML menu.
   The Properties dialog box appears.
3. Click on the Role Navigability option for the *Conference* class.
   The option is highlighted.

   The Properties dialog should look like the one in Figure 31.

Figure 31: Indicating Role Navigability



4. Click **OK**.
   The dialog is dismissed and the property is applied. The display mark for navigability is an arrow pointing to the class that receives service requests.

   Your diagram should resemble Figure 32.

Figure 32: Role Navigability Display Mark



Indicating Relationship Constraints

Constraints are one of the mechanisms provided by the Unified Modeling Language to extend the semantics of standard modeling elements. A constraint on a relationship restricts the values that the relationship can have.

Some relationship constraints are predefined in UML; you can also define your own.

Constraints are not displayed on the class diagram.

Assigning a Constraint

In the Email application, each mailbox has a name that corresponds to the name of the mailbox owner. In this example, you place a constraint on the *Owns* relationship specifying that the name attributes of a *Mailbox* and its associated *Receiver* must match.

Unlike the properties you defined in the previous sections, the constraint property applies to the association itself rather than to one of its roles.

To place a constraint on the *Owns* relationship:

1. Select the arc between the *Receiver* and *Mailbox* classes.
   Selection handles appear on the arc.
2. Choose **Edit Properties** from the UML menu.
   The Properties dialog box appears.
3. Click in the Constraints text field.
4. Type **`names must match`**.
   The Properties dialog should look like the one in Figure 33.

Figure 33: Indicating Constraints



5. Click **OK**.
   The dialog is dismissed and the constraint is applied.

You have now completed a basic class diagram for the Email system. Your diagram should resemble Figure 34.

Figure 34: Class Diagram for the Email Application



Saving the Class Diagram

To save your diagram, choose **Save** from the File menu. Your diagram should be error-free, so you should not receive error messages. If you do, correct the error and save the diagram again.

Continuing the Tutorial

In this chapter, you:

- Started the Class Editor from the StP Desktop
- Created a basic class diagram for the *Email* system
- Used the Properties dialog box to define association characteristics

In the next chapter, you expand the model to include special class and relationship types.

4 Completing the Class Diagram

In this chapter, you expand your class diagram by adding specialized relationships and classes. In addition, you define a stereotype for an Email class.

Modeling Specialized Relationships

Some classes participate in special types of relationships. These relationships include:

- Generalization
- Aggregation
- Composition

In the following sections, you model each of these relationships. You model the relationships by drawing them on the diagram or by using the Object Annotation Editor (OAE).

Modeling Generalizations

A generalization is the relationship between a class, called a superclass, and one or more specializations of the class, called subclasses. Each subclass inherits attributes, operations, and associations from its superclass. In addition, a subclass can have its own attributes and operations that add to or override those of its superclass.

In the Email system, you model one generalization. Since the *Receiver* of a message can be either a *User* or a *Conference*, you model this set of relationships as a generalization. *Receiver* is the superclass, and *User* and *Conference* are the subclasses.

A generalization is often called an "is-a" relationship: a *User* is a *Receiver*, and a *Conference* is a *Receiver.*

Inserting a Generalization

You draw a generalization arc from the subclass to the superclass.

To insert a generalization:

1. Insert an arc from the *User* class to the *Receiver* class.
   Selection handles appear on the arc.
2. Choose **Replace** from the Edit menu.
   The Replace Arc Type dialog appears.

Figure 1: The Replace Arc Type Dialog



3. Choose **Generalization** from the scrolling list.
4. Click **OK**.
   A generalization relationship arc appears, with an arrow pointing to the superclass, *Receiver.*

Contents | Index | Go Back | Previous Page | Next Page | Using StP Help | List of Manuals | Quit Window

5. Repeat the procedure to create a generalization relationship between the *Conference* class and the *Receiver* class.
   Your diagram should resemble Figure 2.

Figure 2: Inserting a Generalization



Modeling Aggregations

An aggregation is a special form of association between a whole (or assembly) and its parts (or components). Instances of the component classes can be assembled into a single instance of the assembly class.

For example, the mail system consists of users and conferences. In your class diagram, *User* and *Conference* are subclasses of *Receiver*. Therefore, you model the relationship between *MailSystem* (the assembly class) and *Receiver* (the component class) as an aggregation.

To create an aggregation, you first draw an association, then you add an annotation to change the association to an aggregation. Annotations are notes and items containing descriptive text and values. You add them using the Object Annotation Editor (OAE).